Data acquisition with the ADS1115 on the raspberry PI

Generated by Doxygen 1.8.17

1 rpi_ads1115	1
2 Class Index	3
2.1 Class List	3
3 Class Documentation	5
3.1 ADS1115rpi Class Reference	5
3.1.1 Detailed Description	5
3.1.2 Member Function Documentation	5
3.1.2.1 hasSample()	5
3.1.2.2 setChannel()	6
3.1.2.3 start()	6
3.2 ADS1115settings Struct Reference	6
3.2.1 Detailed Description	7
Index	9

Chapter 1

rpi_ads1115

Raspberry PI C++ library for the ADS1115

github: https://github.com/berndporr/rpi_ads1115

2 rpi_ads1115

Chapter 2

Class Index

2.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

ADS1115rpi	
This class reads data from the ADS1115 in the background (separate thread) and calls a callback	
function whenever data is available	5
ADS1115settings	
ADS1115 initial settings when starting the device	6

4 Class Index

Chapter 3

Class Documentation

3.1 ADS1115rpi Class Reference

This class reads data from the ADS1115 in the background (separate thread) and calls a callback function whenever data is available.

```
#include <ads1115rpi.h>
```

Public Member Functions

• ~ADS1115rpi ()

Destructor which makes sure the data acquisition has stopped.

• virtual void hasSample (float sample)=0

Called when a new sample is available.

void setChannel (ADS1115settings::Input channel)

Selects a different channel at the multiplexer while running.

void start (ADS1115settings settings=ADS1115settings())

Starts the data acquisition in the background and the callback is called with new samples.

• void stop ()

Stops the data acquistion.

3.1.1 Detailed Description

This class reads data from the ADS1115 in the background (separate thread) and calls a callback function whenever data is available.

3.1.2 Member Function Documentation

3.1.2.1 hasSample()

Called when a new sample is available.

This needs to be implemented in a derived class by the client. Defined as abstract.

6 Class Documentation

Parameters

sample	Voltage from the selected channel
--------	-----------------------------------

3.1.2.2 setChannel()

Selects a different channel at the multiplexer while running.

Call this in the callback handler hasSample() to cycle through different channels.

Parameters

channel Sets the channel from A0A3.

3.1.2.3 start()

Starts the data acquisition in the background and the callback is called with new samples.

Parameters

settings	A struct with the settings.

The documentation for this class was generated from the following file:

• ads1115rpi.h

3.2 ADS1115settings Struct Reference

ADS1115 initial settings when starting the device.

```
#include <ads1115rpi.h>
```

Public Types

```
enum SamplingRates {
    FS8HZ = 0, FS16HZ = 1, FS32HZ = 2, FS64HZ = 3,
    FS128HZ = 4, FS250HZ = 5, FS475HZ = 6, FS860HZ = 7 }
    Sampling rates.
enum PGA { FSR2_048 = 2, FSR1_024 = 3, FSR0_512 = 4, FSR0_256 = 5 }
    Full scale range: 2.048V, 1.024V, 0.512V or 0.256V.
enum Input { AIN0 = 0, AIN1 = 1, AIN2 = 2, AIN3 = 3 }
    Channel indices.
```

Public Attributes

```
• int i2c bus = 1
```

I2C bus used (99% always set to one)

• uint8 t address = DEFAULT ADS1115 ADDRESS

I2C address of the ads1115.

SamplingRates samplingRate = FS8HZ

Sampling rate requested.

PGA pgaGain = FSR2_048

Requested full scale range.

• Input channel = AIN0

Requested input channel (AIN0..AIN3)

• bool initPIGPIO = true

If set to true the pigpio will be initialised.

• int drdy_gpio = DEFAULT_ALERT_RDY_TO_GPIO

GPIO pin connected to ALERT/RDY.

3.2.1 Detailed Description

ADS1115 initial settings when starting the device.

The documentation for this struct was generated from the following file:

• ads1115rpi.h

8 Class Documentation

Index

```
ADS1115rpi, 5
hasSample, 5
setChannel, 6
start, 6
ADS1115settings, 6
hasSample
ADS1115rpi, 5
setChannel
ADS1115rpi, 6
start
ADS1115rpi, 6
```