

Data acquisition with the ADS1115 on the raspberry PI

Generated by Doxygen 1.8.17

1 rpi_ads1115	1
2 Class Index	3
2.1 Class List	3
3 Class Documentation	5
3.1 ADS1115rpi Class Reference	5
3.1.1 Detailed Description	5
3.1.2 Constructor & Destructor Documentation	5
3.1.2.1 ADS1115rpi()	5
3.1.3 Member Function Documentation	6
3.1.3.1 hasSample()	6
3.1.3.2 setChannel()	6
3.1.3.3 start()	6
3.2 ADS1115settings Struct Reference	7
3.2.1 Detailed Description	7
Index	9

Chapter 1

rpi_ads1115

Raspberry PI C++ library for the ADS1115

github: https://github.com/berndporr/rpi_ads1115

Chapter 2

Class Index

2.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

[ADS1115rpi](#)

This class reads data from the ADS1115 in the background (separate thread) and calls a callback function whenever data is available [5](#)

[ADS1115settings](#)

ADS1115 initial settings when starting the device [7](#)

Chapter 3

Class Documentation

3.1 ADS1115rpi Class Reference

This class reads data from the ADS1115 in the background (separate thread) and calls a callback function whenever data is available.

```
#include <ads1115rpi.h>
```

Public Member Functions

- [ADS1115rpi](#) ()
Constructor with the spiDevice.
- [~ADS1115rpi](#) ()
Destructor which makes sure the data acquisition has stopped.
- virtual void [hasSample](#) (float sample)=0
Called when a new sample is available.
- void [setChannel](#) ([ADS1115settings::Input](#) channel)
Selects a different channel at the multiplexer while running.
- void [start](#) ([ADS1115settings](#) settings=[ADS1115settings](#)())
Starts the data acquisition in the background and the callback is called with new samples.
- void [stop](#) ()
Stops the data acquisition.

3.1.1 Detailed Description

This class reads data from the ADS1115 in the background (separate thread) and calls a callback function whenever data is available.

3.1.2 Constructor & Destructor Documentation

3.1.2.1 ADS1115rpi()

```
ADS1115rpi::ADS1115rpi ( )
```

Constructor with the spiDevice.

The default device is /dev/spidev0.0.

Parameters

<i>spiDevice</i>	The raw /dev spi device.
------------------	--------------------------

3.1.3 Member Function Documentation

3.1.3.1 hasSample()

```
virtual void ADS1115rpi::hasSample (
    float sample ) [pure virtual]
```

Called when a new sample is available.

This needs to be implemented in a derived class by the client. Defined as abstract.

Parameters

<i>sample</i>	Voltage from the selected channel
---------------	-----------------------------------

3.1.3.2 setChannel()

```
void ADS1115rpi::setChannel (
    ADS1115settings::Input channel )
```

Selects a different channel at the multiplexer while running.

Call this in the callback handler [hasSample\(\)](#) to cycle through different channels.

Parameters

<i>channel</i>	Sets the channel from A0..A3.
----------------	-------------------------------

3.1.3.3 start()

```
void ADS1115rpi::start (
    ADS1115settings settings = ADS1115settings() )
```

Starts the data acquisition in the background and the callback is called with new samples.

Parameters

<code>settings</code>	A struct with the settings.
-----------------------	-----------------------------

The documentation for this class was generated from the following file:

- `ads1115rpi.h`

3.2 ADS1115settings Struct Reference

ADS1115 initial settings when starting the device.

```
#include <ads1115rpi.h>
```

Public Types

- enum [SamplingRates](#) {
FS8HZ = 0, **FS16HZ** = 1, **FS32HZ** = 2, **FS64HZ** = 3,
FS128HZ = 4, **FS250HZ** = 5, **FS475HZ** = 6, **FS860HZ** = 7 }
Sampling rates.
- enum [PGA](#) { **FSR2_048** = 2, **FSR1_024** = 3, **FSR0_512** = 4, **FSR0_256** = 5 }
Gains of the PGA.
- enum [Input](#) { **AIN0** = 0, **AIN1** = 1, **AIN2** = 2, **AIN3** = 3 }
Channel indices.

Public Attributes

- int [i2c_bus](#) = 1
I2C bus used (99% always set to one)
- uint8_t [address](#) = DEFAULT_ADS1115_ADDRESS
I2C address of the ads1115.
- [SamplingRates](#) [samplingRate](#) = FS8HZ
Sampling rate requested.
- [PGA](#) [pgaGain](#) = FSR2_048
Requested gain.
- [Input](#) [channel](#) = AIN0
Requested input channel (0 or 1)
- bool [initPIGPIO](#) = true
If set to true the pigpio is initialised.
- int [drdy_gpio](#) = DEFAULT_DATA_READY_GPIO
Default GPIO pin for data ready.

3.2.1 Detailed Description

ADS1115 initial settings when starting the device.

The documentation for this struct was generated from the following file:

- `ads1115rpi.h`

Index

- ADS1115rpi, [5](#)
 - ADS1115rpi, [5](#)
 - hasSample, [6](#)
 - setChannel, [6](#)
 - start, [6](#)
- ADS1115settings, [7](#)
- hasSample
 - ADS1115rpi, [6](#)
- setChannel
 - ADS1115rpi, [6](#)
- start
 - ADS1115rpi, [6](#)